


Cherry G80-2551 ** updated 2020-04-26



10 function keys on left cluster

	<p><u>Hid_listen:</u> At first press: r19 rF0 r19</p> <p>The mute/unmute toggles back and forth (on/off)</p> <p>Second key press: r19 rF0 !CS2_F0! I60737 X61239 r19 W61240 R61741 wF2 rFA rAB r86 ID:AB86(2) S61747 wED rFA w02 rFA L61754</p> <p>Xev: No output, key press does not do anything to xev</p>	<p>r5F rF0 r5F</p> <p>KeyRelease event, serial 38, synthetic NO, window 0x5e00001, root 0x1da, subw 0x0, time 5871881, (-353,153), root:(508,608), state 0x10, keycode 202 (keysym 0x0, NoSymbol), same_screen YES, XLookupString gives 0 bytes: XFilterEvent returns: False</p>
	<p>r39 rF0 r39</p> <p>The vol + repeats automatically until full volume</p> <p>Xev:</p>	<p>rE1 r14 r77 rE1 rF0 r14 rF0 r77</p> <p>KeyPress event, serial 38, synthetic NO, window 0x5e00001, root 0x1da, subw 0x0, time 6177324, (284,191), root:(1145,646),</p>

	<p>No output, key press does not do anything to xev</p>	<p>state 0x10, keycode 127 (keysym 0xff13, Pause), same_screen YES, XLookupString gives 0 bytes: XmbLookupString gives 0 bytes: XFilterEvent returns: False</p>
	<p>First key press: r53 rF0 r53</p> <p>r5C rF0 r5C</p> <p>Second key press: r53 rF0 !CS2_F0! I35522 X36023 r53 W36025 R36526 wF2 rFA rAB r86 ID:AB86(2) S36532 wED rFA w02 rFA L36539</p> <p>Xev: FocusIn event, serial 35, synthetic NO, window 0x5e00001, mode NotifyUngrab, detail NotifyAncestor</p> <p>KeymapNotify event, serial 35, synthetic NO, window 0x0, keys: 2 0</p>	<p>r50 rF0 r50</p> <p>FocusIn event, serial 35, synthetic NO, window 0x5e00001, mode NotifyUngrab, detail NotifyAncestor</p> <p>KeymapNotify event, serial 35, synthetic NO, window 0x0, keys: 2 0</p>
	<p>rE0 r12 rE0 r7C rE0 rF0 r7C rE0 rF0 r12</p> <p>EnterNotify event, serial 38, synthetic NO, window 0x5c00001, root 0x1da, subw 0x0, time 6509804, (172,102), root:(1033,557), mode NotifyNormal, detail NotifyAncestor, same_screen YES, focus YES, state 16</p>	<p>r6F rF0 r6F</p> <p>on second key press I get often r6F rF0 !CS2_F0! I62585 X63087 r6F W63088 R63589 wF2 rFA rAB r86 ID:AB86(2) S63594 wED rFA w02 rFA L63602</p> <p>Xev:</p>

	<pre>KeymapNotify event, serial 38, synthetic NO, window 0x0, keys: 75 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0</pre>	No output
	<pre>r5C rF0 r5C The win/menu key seems to repeat endless; if I press d after this key, desktop is shown like win+d FocusIn event, serial 35, synthetic NO, window 0x5600001, mode NotifyUngrab, detail NotifyAncestor KeymapNotify event, serial 35, synthetic NO, window 0x0, keys: 2 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0</pre>	<pre>r48 rF0 r48 FocusIn event, serial 35, synthetic NO, window 0x5600001, mode NotifyUngrab, detail NotifyAncestor KeymapNotify event, serial 35, synthetic NO, window 0x0, keys: 2 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0</pre>